Connect to cdfdca as enstore:

```
$ ssh enstore@cdfdca
```

Start the dCache Admin program:

```
$ adcache
```

- Note that the "up-arrow to retrieve the previous command line" trick does NOT work within the adcache program, nor does using the arrow keys to navigate forward or backward through the command line.
- Next page...

 Your new prompt will display the area you are in. You start by default in the "local" area, so the prompt is this:

```
(local) enstore >
```

 For brevity, the adcache prompt will be presented for the rest of this document as just:

Next page...

 The pool group to which a pool is assigned is defined in the "PoolManager" area. Switch into the area from the "local" area with:

> cd PoolManager

- Moving a pool between pool groups involves two steps: removing it from its current pool group and adding it to its new pool group. To look up what pool group a particular pool is currently in, use the Pool Selection Configuration web pages.
- Next page...

- To remove a pool from a pool group, type:
 - > psu removefrom pgroup <group> <cellname>
 where <group> is the name of the current pool group and <cellname>
 is the name of the pool you want to move, as found on the
 dCache ONLINE page
 - Example:
 - > psu removefrom pgroup readPools r-fcdfdata139-1
- To add a pool to a pool group, type:
 - > psu addto pgroup <group> <cellname> where <group> is the name of the new pool group and <cellname> is the name of the pool you want to move, as found on the dCache ONLINE page
 - Example:
 - > psu addto pgroup TestPools r-fcdfdata139-1
- Next page...

- To move an entire node between pool groups, there is no shortcut. You must explicitly move each and every pool.
- If you need to return to the "local" area of adcache, use:

> ..

- To quit adcache, use Ctrl-D.
- Done!